





9Locker

Quick Startup Guide

Ver 1.0.03 Sep 2017

- 9Locker Manager





Contents

App Installation

Initial Setup

Settings

Start Working

Group
Operations



Minimum
Requirements

9Locker Manager Installation


1
Download 9Locker Client.

2
9Locker Manager should be installed on the administrator computer.


3
Execute the installation file as Administrator.




Click Next



Click Next



Check "I accept.." and click Next



Click Install

Click Finish

8

9Locker Manager Initial Setup


1
First we need to add some clients.

2
We will now define group of users.

3
Click on Groups Button



4



Enter Group Name and then click 'add'


5
Click Close

6
Click on Users Button



Enter User Name Details And Click 'Save'


7



- You can enter either Computer Name or IP
- Select Group

8
Click Close

9
You will now see the user under the group you've created.





- Contents
- App Installation
- Initial Setup
- Start Working**
- Group Operations
- Minimum Requirements


9Locker Manager – Start Working

1
After you've installed the clients , you are now able to control them.

2
Select the client you want to control by checking it over the tree control.



3



The interface displays a remote client desktop preview at the top. Below it, a control panel includes fields for Full Name (johnd), Group (Sales), IP Address (192.168.0.148), Status (OFF), Last Login, and Last Logout. At the bottom, there is a grid of icons for various operations: Lock Client, Unlock Client, Change Client Password, Change Client Pattern, Change Client Locker Background, Get Client Operations Log, Change Client Locker Settings, and Send Message To Client.

Remote Client Desktop Preview

Icon	Operation
	Lock Client
	Unlock Client
	Change Client Password
	Change Client Pattern
	Change Client Locker Background
	Get Client Operations Log
	Change Client Locker Settings
	Send Message To Client



9Locker Manager – Lock Client

Operation : Lock Client

Icon	Operation
	Lock Client
	Unlock Client
	Change Client Password
	Change Client Pattern
	Change Client Locker Background
	Get Client Operations Log
	Change Client Locker Settings
	Send Message To Client

- Contents
- App Installation
- Initial Setup
- Start Working**
- Group Operations
- Minimum Requirements

1

Select the client you want to control By checking it over the tree control.

2

Click on the Lock Button

4

Click on the Refresh Button









5

You can now see on the preview screen that the locker is activated.




9Locker Manager – Unlock Password

Operation : Unlock Client

Icon	Operation
	Lock Client
	Unlock Client
	Change Client Password
	Change Client Pattern
	Change Client Locker Background
	Get Client Operations Log
	Change Client Locker Settings
	Send Message To Client


1
Select the client you want to control By checking it over the tree control.



2
Click on the Unlock Button



Works only when the client is Locked



You can now see on the preview screen that the locker is deactivated.

Contents

App Installation

Initial Setup









Start Working

Group Operations


Minimum Requirements

9Locker Manager – Change Client Password

Operation : Change Client Password

Icon	Operation
	Lock Client
	Unlock Client
	Change Client Password
	Change Client Pattern
	Change Client Locker Background
	Get Client Operations Log
	Change Client Locker Settings
	Send Message To Client

1
Select the client you want to control by checking it over the tree control.



2
Click on the Change Password Button



Works only when the client is Locked

3
Change User Password











Change user password and click 'Save'


4
Click Close

9Locker Manager – Change Client Pattern

Operation : Change Client Pattern

Icon	Operation
	Lock Client
	Unlock Client
	Change Client Password
	Change Client Pattern
	Change Client Locker Background
	Get Client Operations Log
	Change Client Locker Settings
	Send Message To Client


1
Select the client you want to control by checking it over the tree control.



2
Click on the Change Pattern Button



Works only when the client is Locked











Draw Pattern **Twice**
And click Save


4
Click Close

9Locker Manager – Change Client Locker Background

Operation : Change Client Locker Background

Icon	Operation
	Lock Client
	Unlock Client
	Change Client Password
	Change Client Pattern
	Change Client Locker Background
	Get Client Operations Log
	Change Client Locker Settings
	Send Message To Client


Select the client you want to control by checking it over the tree control.



Click on the Change Background Button



Works only when the client is Locked



- Click [..] Button to open dialog.
- Select Image Type (PNG/JPEG)
- Select Image
- Then Click 'Save'

Click Close

Contents

App Installation

Initial Setup









Start Working

Group Operations


Minimum Requirements

9Locker Manager – Get Client Operations Log

Operation : Get Client Operations Log

Icon	Operation
	Lock Client
	Unlock Client
	Change Client Password
	Change Client Pattern
	Change Client Locker Background
	Get Client Operations Log
	Change Client Locker Settings
	Send Message To Client

Select the client you want to control by checking it over the tree control.



Click on the Client Operation Log Button



User Log

Select Period: Week

ID	TIME	ACTION	USER
14	9/7/2017 3:55:25 PM	Lock	LocalUser
12	9/7/2017 3:48:54 PM	Lock	LocalUser
9	9/7/2017 3:22:36 PM	Lock	LocalUser
3	9/7/2017 2:10:43 PM	Lock	LocalUser
1	9/7/2017 12:05:41 PM	Lock	LocalUser
7	9/7/2017 2:12:52 PM	Set Background	Administrator
4	9/7/2017 2:12:08 PM	Set Background	Administrator
10	9/7/2017 3:42:29 PM	Set Pattern	LocalUser
6	9/7/2017 2:12:19 PM	Set Pattern	LocalUser
5	9/7/2017 2:12:14 PM	Set Pattern	LocalUser
13	9/7/2017 3:49:01 PM	Unlock	Administrator
11	9/7/2017 3:48:43 PM	Unlock	Administrator
8	9/7/2017 3:17:16 PM	Unlock	Administrator
2	9/7/2017 12:05:43 PM	Unlock	LocalUser

close

• Select Date Range :
Day/Week/Month/Year/All

Note:

Local User = User Operation

Administrator = Admin Operations

Click Close




9Locker Manager – Change Client Locker Settings

Operation : Change Client Locker Settings

Icon	Operation
	Lock Client
	Unlock Client
	Change Client Password
	Change Client Pattern
	Change Client Locker Background
	Get Client Operations Log
	Change Client Locker Settings
	Send Message To Client

Select the client you want to control by checking it over the tree control.



Click on the Client Locker Settings Button



Change User Settings

General Settings

☐ Hide Pattern Line

☒ Load 9Locker Pro on startup

Trigger Settings

Trigger those events after 3 Failures.

☒ Play Alarm Sound

☒ Send Mail Alert

☒ Capture User Camera Video To Email

Email Settings

email

password

SMTP server

SMTP Port

☒ Enable SSL ☐ Requires Authentication









send close

- Select Date Range :
Day/Week/Month/Year/All
- Note:**
Local User = User Operation
Administrator = Admin Operations


Action	Explain
Hide Pattern Line	The pattern line will be invisible when checked.
Load 9Locker Pro on startup	The client will start automatically when Windows Start.
Trigger those events after x times	After (X) times the checked actions will be executed : [x] Play Alarm Sound [x] Send Mail Alert [x] Capture User Camera video to email
Email Settings	In order to send the user notifications to his email fill email account.

9Locker Manager – Send Message To Client

Operation : Send Message To Client

Icon	Operation
	Lock Client
	Unlock Client
	Change Client Password
	Change Client Pattern
	Change Client Locker Background
	Get Client Operations Log
	Change Client Locker Settings
	Send Message To Client


1
Select the client you want to control by checking it over the tree control.



2
Click on the Change Send Message Button



Works only when the client is Locked



- Enter Message
- Click 'Send'

4
Click Close

 07/09/2017 16:41:31 - Coffe Break! at 2PM

- This is what the client will see.
- If the user clicks on the message It will be confirmed and disappear.

9Locker Manager – Advanced Operations

Contents

App Installation









Initial Setup

Start Working


**Group
Operations**

Minimum
Requirements

Operation : Group Operations

Icon	Operation
	Lock Client
	Unlock Client
	Change Client Password
	Change Client Pattern
	Change Client Locker Background
	Get Client Operations Log
	Change Client Locker Settings
	Send Message To Client

1
Select the **group** you want to control by checking it over the tree control.



2
Click on the Selected Operation



**Works only when the client is Locked
(Except : Lock Client)**



9Locker Manager – Minimum Requirements

Contents

App Installation

Initial Setup

Start Working

Group
Operations

**Minimum
Requirements**



Item	Type
OS	Windows XP/7/8/10
CPU	Dual Core & Up 1.2Ghz
Memory	2 Gb
HDD	128 Gb
Network Card	10/100



Item	Type
9Locker Port	9090
9Locker Service Port	9091



Contents

App Installation

Initial Setup

Start Working

Group
Operations

Minimum
Requirements

Contact

Contact Us:

Leizersoft

@Site : www.leizersoft.com

@Email : royleizer@gmail.com